



# **Surefox Pro Setup Guide**

# 1. Introduction

Surefox Pro is recommended software for preventing unauthorised access to tablets used for Staffsavvy Clock In Screens.

Surefox Pro has a vast array of configuration options and we've only listed the key changes from default within the guide.

Surefox Pro supports remotely configuring the devices and also temporarily exporting the settings for import to another device. This is done via the 42Gear's (Surefox's developers) site and works well for quick replication of settings.

Each of the sections in this guide refers to the setting within Surefox's Settings menu.

In addition to these settings we recommend setting a PIN code for the tablet and changing the admin PIN for Surefox itself. Surefox's PIN is changed under Browser Settings in the Surefox Settings menu.

Additional options can be set on Surefox to bespoke the experience for you; this guide just covers the basic recommended settings to get the system working.

As always, please get in touch if you have any questions or suggestions. Email us at [support@staffsavvy.com](mailto:support@staffsavvy.com)

## 2. Allowed Websites

Add a single URL for the clock in screens.

- URL:  
https://[your Staffsavvy domain]/clockin
- Display Name:  
[Optional]
- Allow Only This Page:  
[unchecked]
- Set as Starting URL:  
[enabled]

## 3. Browser Preferences

- Enable Javascript:  
[enabled]
- Enable Plug-in Support:  
[enabled]

- Camera Access:  
[always grant] (if you wish to use the webcam option)
- Use Back Button for Browsing  
[disabled]
- Enable Auto Media Playback:  
[enabled]
- Detect Network Connection:  
[enabled]
- Tabbed Browsing:
  - Enable Tabbed Browsing:  
[unchecked]
- Idle Timeout:  
Disabled
- Advanced Browser Settings
  - Browser Engine:  
XWalk
  - Work Offline:  
[unchecked]
  - Enable DOM Storage:  
[enabled]
  - Enable Database Storage:  
[enabled]
- Accept Cookies:  
[enabled]
- Enable Cache:  
[enabled]
- Cache Browsing:  
[unchecked]
- Save Form Data:  
[unchecked]
- On Homepage Load:
  - Clear Cache:  
[unchecked]
  - Clear Cookies:  
[unchecked]
- Disable Volumn Buttons:  
[checked]

## 4. SureFox Pro Settings

- Enable Kiosk Mode:  
[enabled]
- Disable Status Bar:  
[enabled]

- Disable Bottom Bar:  
[enabled]
- Enable Home Key:  
[unchecked]
- Disable Hardware Keys:  
[enabled] to all

## 5. Display Settings

- Enable Zoom:  
[unchecked]
- Show Title Bar:  
[unchecked]
- Full Screen Mode:  
[enabled]
- Disable Bottom Bar:  
[enabled]
- Prevent Suspend:
  - Prevent Suspend Settings:  
[enabled]